## **CUSTOMER SERVICE BULLETIN**



Bulletin No.	45Ø2-Ø3(Correction 2)
	Inventory Management
Model	Model II
Stock No.	26-45Ø2 Version 1.1
Date	Feb. 22, 1982
Page 1 of	1

400 Atrium-One Tandy Center, Fort Worth, Texas 76102

## **Problem**

There is a problem when the original master disk is run when you wish to re-unitialize the system or change the parameters.

## **Solution**

If this problem occurs in the IMS system, the following must be done to clear out the system information. This should only be done in cases when there is not a clean master available.

- 1. At "TRSDOS Ready", type BASIC -F:3
- 2. When BASIC has loaded, enter the following program:

1Ø CLEAR 1ØØØ
2Ø KILL "SALEDATA/DAT":KILL"CONTROL/DAT"
3Ø OPEN"R",1,"CONTROL/DAT",96
4Ø FIELD1, 96 AS X\$:LSETX\$=STRING\$(96,32):PUT1,1
5Ø LSETX\$=STRING\$(96,Ø)
6Ø FORF=2TO5:PUT1,F:NEXTF:CLOSE
7Ø SYSTEM"IMS"

Then type RUN and press <ENTER>
 Type SYSTEM to get to TRSDOS READY and make a backup.